



Zen Flash Gallery
version 1.0

User Guide

Contents

Starting the Work	2
SWF Object HTML Code	2
Configuring the Gallery	2
XML File Format	3
Gallery Parameters	4

Starting the Work

To start working simply paste object HTML into your page and setup xml configuration file. You can place configuration file anywhere on your server.

SWF Object HTML Code

Paste this code into your HTML-page and replace object stage parameter with your values. The following HTML-code supports MS Internet Explorer and Mozilla Firefox:

```
<object classid="clsid:D27CDB6E-AE6D-11cf-96B8-444553540000"
codebase="http://download.macromedia.com/pub/shockwave/cabs/flash/swflash.cab#version=6,0,29,0"
width="width" height="height">
<param name="movie" value="swf file path">
<param name="quality" value="high">
<param name="scale" value="noscale">
<param name="bgcolor" value="background color">
<param name="flashVars" value="XMLFile=path to configuration file">

<embed src="swf file path" width="width" height="height" flashvars="XMLFile=path to configuration
file" quality="high" pluginspage="http://www.macromedia.com/go/getflashplayer" type="application/x-
shockwave-flash" scale="noscale" bgcolor="background color"></embed>
</object>

<!-- You can't remove the copyright text below if you're using free version -->
<span style="font-size:.7em">&copy;copyright <a href="http://flash-gallery.com/"
title="Flash-Gallery.com - Zen flash gallery free version">Flash-Gallery.com</a> </span>
```

Configuring the Gallery

An XML file is used to configure the gallery. By editing the XML file, you can add or remove gallery images as well as edit multiple appearance and behavior settings. The format of the XML file is described below.

Gallery settings are described in the **<settings></settings>** tag of the XML file as follows:

<parameter name> parameter value </parameter name>.

For example, the background color is configured using the tag **<backgroundColor>0xAAC5D8</backgroundColor>**.

All the file information is contained in the **<album> </album>** structure.

```
<album icon="" thumbnailsFolder="" imagesFolder="" description="">
  <image name="" description="" thumbnail=""/>
  <image name="" description="" thumbnail=""/>
  <image name="" description="" thumbnail=""/>
</album>
```

icon – name and location of the icon album image.

thumbnailsFolder – Path to the folder with thumbnail images.

imagesFolder – Path to the folder with album images

image name – Image name

description – Image description

thumbnail – thumbnail file name

XML File Format

```
<gallery>
  <settings>
    <frameSize>5</frameSize>
    <frameColor>0xFFFFFFFF</frameColor>
    <cornerRadius>7</cornerRadius>
    <backgroundColor>0xAAC5D8</backgroundColor>
    <initialState>Load Image</initialState>
    <showCaption>Always</showCaption>
    <captionBackgroundAlpha>41</captionBackgroundAlpha>
    <captionBackgroundCornerRadius>4</captionBackgroundCornerRadius>
    <buttonsBackgroundAlpha>41</buttonsBackgroundAlpha>
    <buttonsBackgroundCornerRadius>4</buttonsBackgroundCornerRadius>
    <showButtons>Always</showButtons>
    <showAlbumsButton>true</showAlbumsButton>
    <showThumbnailsButton>true</showThumbnailsButton>
    <showSlideshowButton>true</showSlideshowButton>
    <showNavigationButton>true</showNavigationButton>
    <rotationDirection>Vertical CW</rotationDirection>
    <rotationDuration>700</rotationDuration>
    <panelBackgroundAlpha>43</panelBackgroundAlpha>
    <iconWidth>90</iconWidth>
    <iconHeight>55</iconHeight>
    <iconPadding>10</iconPadding>
    <rotationSound></rotationSound>
    <clickSound></clickSound>
    <overSound></overSound>
  </settings>
  <albums>
    <album icon="" thumbnailsFolder="" imagesFolder="" description="">
      <image name="" description="" thumbnail=""/>
      <image name="" description="" thumbnail=""/>
      <image name="" description="" thumbnail=""/>
    </album>
    <album icon="" thumbnailsFolder="" imagesFolder="" description="">
      <image name="" description="" thumbnail=""/>
      <image name="" description="" thumbnail=""/>
      <image name="" description="" thumbnail=""/>
    </album>
    <album icon="" thumbnailsFolder="" imagesFolder="" description="">
      <image name="" description="" thumbnail=""/>
      <image name="" description="" thumbnail=""/>
      <image name="" description="" thumbnail=""/>
    </album>
  </albums>
</gallery>
```

Gallery Parameters

Parameter Name	Description
cacheRadius	Radius of gallery cash
dropShadow	Show/hide gallery shadow
frameSize : Number	Frame thickness
frameColor : Number	Frame color. Format : 0xRRGGBB
cornerRadius : Number	Corner radius for gallery background and gallery frame
backgroundColor : Number	Background color inner frame for the first time downloading images. Default : 0xAAC5D8
initialState :String	Initial state of the gallery. Possible values : Load Image, Start Slideshow, Show Albums, Show Thumbnails. Default : Start Slideshow.
showCaption :String	Defines when to show an image caption. Possible values : Always, Never, onMouseOver.
captionBackgroundAlpha : Number	Caption background transparency. Default : 41. Possible values : (0-100).
captionBackgroundCornerRadius : Number	Corner radius of caption background. Default : 4
buttonsBackgroundAlpha : Number	Buttons background transparency. Default : 41. Possible values : (0-100).
buttonsBackgroundCornerRadius : Number	Corner radius of buttons Background. Default : 4
showButtons : String	Defines when to show the buttons. Possible values : Always, Never, onMouseOver. Default : Always

Parameter Name	Description
showAlbumsButton: Boolean	Show/hide albums button. Default: true
showThumbnailsButton: Boolean	Show/hide thumbnails button. Default: true
showSlideshowButton: Boolean	Show/hide “play / pause” buttons. Default: true
showNavigationButton: Boolean	Show/hide “next / previous” buttons. Default: true
rotationDirection: String	Rotation direction. Possible values: Vertical CW, Vertical CCW, Horizontal CW, Horizontal CCW. Default: Vertical CW.
rotationDuration: Number	Duration of rotation (in milliseconds). Default: 700.
panelBackgroundAlpha: Number	Transparency of panel icons and albums. Default: 43 (0-100).
iconWidth: Number	Icons width. Default: 90
iconHeight: Number	Icon height. Default: 55
iconPadding: Number	Distance between icons in the list. Default: 10
XMLFile: String	Full Path to XML configuration file (contains filename). Default: no.
rotationSound: String	Path to rotation sound file with rotation. Default: no.
clickSound: String	Path to the file with sound of click. Default: no.
overSound: String	Path to the file with sound of mouseover. Default: no.

Parameter Name	Description
cacheRadius	Radius of gallery cash
dropShadow	Show/hide gallery shadow
frameSize : Number	Frame thickness
frameColor : Number	Frame color. Format : 0xRRGGBB
cornerRadius : Number	Corner radius for gallery background and gallery frame
backgroundColor : Number	Background color inner frame for the first time downloading images. Default : 0xAAC5D8
initialState :String	Initial state of the gallery. Possible values : Load Image, Start Slideshow, Show Albums, Show Thumbnails. Default : Start Slideshow.
showCaption :String	Defines when to show an image caption. Possible values : Always, Never, onMouseOver.
captionBackgroundAlpha : Number	Caption background transparency. Default : 41. Possible values : (0-100).
captionBackgroundCornerRadius : Number	Corner radius of caption background. Default : 4
buttonsBackgroundAlpha : Number	Buttons background transparency. Default : 41. Possible values : (0-100).
buttonsBackgroundCornerRadius : Number	Corner radius of buttons Background. Default : 4
showButtons : String	Defines when to show the buttons. Possible values : Always, Never, onMouseOver. Default : Always
showAlbumsButton : Boolean	Show/hide albums button. Default : true

Parameter Name	Description
showThumbnailsButton: Boolean	Show/hide thumbnails button. Default: true
showSlideshowButton: Boolean	Show/hide “play / pause” buttons. Default: true
showNavigationButton: Boolean	Show/hide “next / previous” buttons. Default: true
rotationDirection: String	Rotation direction. Possible values: Vertical CW, Vertical CCW, Horizontal CW, Horizontal CCW. Default: Vertical CW.
rotationDuration: Number	Rotation duration (in milliseconds). Default: 700.
panelBackgroundAlpha: Number	Transparency of panel icons and albums. Default: 43 (0-100).
iconWidth: Number	Icons width. Default: 90
iconHeight: Number	Icon height. Default: 55
iconPadding: Number	Distance between icons in the list. Default: 10
XMLFile: String	Full Path to XML configuration file (contains filename). Default: no.
rotationSound: String	Path to rotation sound file with rotation. Default: no.
clickSound: String	Path to the file with sound of click. Default: no.
overSound: String	Path to the file with sound of mouseover. Default: no.